

Groups







Once a profile for a user has been defined, the user can be assigned to one or more user groups. The user inherits all authorizations and session profiles defined for the groups to which he or she is assigned.

This chapter covers the following topics:

- Overview of Defined Groups
 - Information About a Group
 - Adding a Group
 - Updating a Group
 - General Properties
 - Users
 - Allowed Sessions
 - Configured Sessions
-

Overview of Defined Groups

When you select the "Groups" object in the tree-view frame, a list of all defined groups appears in the detail-view frame.

Groups Properties		
	Property	Value
	Service status	Stopped
	Number of Groups	4
	group1	Description for Group1
	group2	Description for Group2
	group3	Description for Group3
	testgroup	Group for testing







Commands

The following command button is available in the command frame:

Add New Group	Add a new group. See <i>Adding a Group</i> .
----------------------	--

Information About a Group

When you expand the "Groups" object and then select a group in the tree-view frame, a list of all defined users and allowed sessions appears in the detail-view frame.

Group Details		
	Property	Value
	testgroup	Group for testing
	kol	Karin Olivier
	test	Test user
	tpi	
	Allowed sessions	
	BS2000	
	IBM	

Commands

The following command buttons are available in the command frame:

Delete Group	Deletes the selected group. You will be asked to confirm the deletion.
Modify Group	Display and/or modify the selected group. See <i>Updating a Group</i> .
Copy Group	Copies the selected group. Specify a name in the resulting dialog and choose the Save button.


Adding a Group

You do not have to stop the Entire Screen Builder Server. You can also add groups when the server is running.

▶ To add a group

1. Select the "Groups" object in the tree-view frame.
2. Choose the **Add New Group** button.

The Group dialog appears.



3. Specify a name for the group.
 4. Choose the **OK** button.
- The Add New Group dialog appears.
5. Specify all required properties (see the property descriptions below).
 6. Choose the **Update Group** button at the bottom of the detail-view frame.

Updating a Group

You do not have to stop the Entire Screen Builder Server. You can also update groups when the server is running.

▶ To update a group

1. Expand the "Groups" object and select the desired group in the tree-view frame.
2. Choose the **Modify Group** button.

The Modify Group dialog appears.

3. Modify all required properties (see the property descriptions below).
4. Choose the **Update Group** button at the bottom of the detail-view frame.

General Properties

Add New Group		
	Property	Value
	Group name:	testgroup
	Group description:	<input type="text"/>

Group name


The name can only be specified when adding a new group. Later, this text box cannot be modified.

Group description

A brief description for the group.

Users

You can add any user that has previously been defined. See *Users*.


	Users:	<input type="text"/>	<input type="button" value="Add/Delete"/>
---	--------	----------------------	---

When users have already been added to the group, they are shown in the list box.

► **To add or remove users to/from the group**

1. Choose the **Add/Delete** button.

The Add/Delete User dialog appears.



All users that have not yet been added to the group are shown in the Available Items list box on the left. Users that have already been added are shown in the Selected Items list box on the right.

2. Choose one of the following command buttons:

Add	Add the selected available user to the group.
Add All	Add all available users to the group.
Delete	Delete the selected user from the group.

3. Choose the **OK** button.


Allowed Sessions

You can allow any session that has previously been defined. See *Host Sessions*.

If **Allow all sessions for all users** has been activated in the server settings, this overwrites the settings for the groups.

Important:

You have to allow at least one session for the group. Otherwise, the users in this group cannot start a host session.




When sessions have already been allowed for the group, they are shown in the list box.

► To allow or diallow sessions for the group

1. Choose the **Add/Delete** button.

The Add/Delete Sessions dialog appears.



All sessions that have not yet been allowed for the group are shown in the Available Items list box on the left. Sessions that have already been allowed are shown in the Selected Items list box on the right.

2. Choose one of the following command buttons:

Add	Allow the selected available session.
Add All	Allow all available sessions.
Delete	Disallow the selected session.

3. Choose the **OK** button.


Configured Sessions

You can modify some of the session properties (for example, color scheme and key scheme).

If **Allow all sessions for all users** has been activated in the server settings, each session can be configured. The allowed sessions (see above) are not considered in this case.

If **Allow all sessions for all users** has been deactivated, the allowed sessions are considered. In this case, it is only possible to configure the sessions that have been allowed.

Two steps are required: first, you select a session for configuration and then you configure the session (see below).




When sessions have already been selected for configuration, they are shown in the list box.

► To select a session for configuration

1. Choose the **Add/Delete** button.

The Add/Delete Configurable Sessions dialog appears.



The sessions that have not yet been selected for configuration are shown in the Available Items list box on the left. Sessions that have already been selected for configuration are shown in the Selected Items list box on the right.

2. Choose one of the following command buttons:


Add	Add the selected available session.
Add All	Add all available sessions.
Delete	Delete the selected session.

3. Choose the **OK** button.

► To configure a session







1. Choose the **Configure** button.

The Configured Sessions in Group dialog appears.



2. Select the session to be configured.
3. Choose the **Select** button.

The Configure Session dialog appears. For example:

Configure Session si14		
	Terminal Viewer Property	Value
	Text blink rate:	<input type="text" value="750"/>
	Cursor blink rate:	<input type="text" value="250"/>
	Session font:	<input type="text" value="Courier New"/>
	Property	Value
	Color scheme:	<input type="text" value="bs2cols"/>
	Key scheme:	<input type="text" value="bs2keys1"/>
	BS2000 P-key scheme:	<input type="text" value="--- None ---"/>

4. Modify all required properties.

A detailed description of these properties can be found in the section *Host Sessions*.

The following properties apply only to Terminal Viewer sessions: **Text blink rate**, **Cursor blink rate** and **Session font**.

The property **BS2000 P-key scheme** is only shown for sessions of type BS2000.

5. Choose the **Update Session** button to save your modifications.

To delete a configured session

1. Choose the **Configure** button.

The Configured Sessions in Group dialog appears.

2. Select the session to be deleted.
3. Choose the **Delete Profile** button.